

目录

中文使用说明	1
如何在 UOS 系统下运行安装包:	2
如何在 Kylin 系统下运行安装包:	3
如何在 Deepin 系统下运行安装包:	4
如何卸载 Anytxt:	5
Instructions for use	6
How to run the installer under Ubuntu system:.....	6
How to uninstall Anytxt:.....	7

中文使用说明

特别说明：

安装前请先查看本机的 CPU 类型确定合适的安装包。

aarch64(ARM64)版本适用的 CPU：


飞腾(Phytium)、麒麟(Kirin)、鲲鹏(Kunpeng)、骁龙 (Snapdragon)、ARM64、AArch64、M1、M2 等 CPU 架构上的 UOS、Kylin、凝思、中科方德、Deepin、Ubuntu、CentOS 等 Linux 内核系统。

x86_64(AMD64)版本适用的 CPU：

兆芯、海光(HYGON)、英特尔 Intel、AMD 等 CPU 架构上的 UOS、Kylin、凝思、中科方德、Deepin、Ubuntu、CentOS 等 Linux 内核系统。


如何在 UOS 系统下运行安装包：

1. 将下载的压缩包解压，右键单击被解压的 anytxt.run
2. 在弹出的右键菜单栏中点击“属性”
3. 在弹出的属性窗口中展开“权限管理”
4. 在展开的权限管理中勾选“允许以程序执行”
5. 鼠标双击 anytxt.run，点击“运行”即可开始执行安装程序



如何在 Kylin 系统下运行安装包：

1. 将下载的压缩包解压，右键单击被解压的 anytxt.run
2. 在弹出的右键菜单栏中点击“属性”
3. 在弹出的属性窗口顶部选中“权限”窗口
4. 在权限窗口中的“拥有者”用户所在的勾选框，勾选“可执行”
5. 点击确定按钮，保存修改
6. 鼠标双击 anytxt.run，点击“直接运行”即可开始执行安装程序



如何在 Deepin 系统下运行安装包：


1. 将下载的压缩包解压，右键单击被解压的 anytxt.run
2. 在弹出的右键菜单中点击“属性”
3. 在弹出的属性窗口中展开“权限管理”
4. 在展开的权限管理中勾选“允许以程序执行”
5. 鼠标双击 anytxt.run，点击“运行”即可开始执行安装程序



如何卸载 Anytxt:


方法一:

1. 在 UOS、Kylin、Deepin 等系统环境下进入 Anytxt 安装目录: /opt/apps/com.cbewin.anytxt
2. 鼠标双击目录中的 uninstall 程序, 点击“运行”即可卸载程序



方法二:


1. 在桌面右击, 在菜单栏中选择“在终端中打开”
2. 在终端输入命令: `cd /opt/apps/com.cbewin.anytxt`, 按下 Enter 键进入 Anytxt 安装目录
3. 输入命令: `./uninstall`, 按下 Enter 键即可卸载程序



Instructions for use

How to run the installer under Ubuntu system:


1. Extract the downloaded zip file and right-click on the extracted anytxt.run.
2. Click "Properties" in the pop-up right-click menu bar.
3. Check the "Permissions" window at the top of the Properties pop-up window.
4. Check the "Allow file execution" box in the permissions window.
5. Right-click anytxt.run and click "Run as program" in the pop-up menu bar to execute the installer.



How to uninstall Anytxt:

Method one:

1. Enter the Anytxt installation directory: `/opt/apps/com.cbewin.anytxt`.
2. Double-click the uninstall program in the directory.



Method two:

1. Right-click on the desktop and select "Open in Terminal" in the menu bar.
2. Enter the command: `cd /opt/apps/com.cbewin.anytxt` in the terminal, and press Enter to enter the Anytxt installation directory.
3. Enter the command: `./uninstall`, press Enter to uninstall the program.

